

Installing the software

You can install PrivateGSM on your mobile device by sending an installation email/SMS from the web site of the product or with your PC (via Bluetooth or USB port) via AppStore for iPhone or via Google Play Store for Android. Once the installation file is downloaded the installation wizard completes the setup.

Installation via email/SMS message



The phone must have Internet access for this type of installation.

To download, install and activate the software via email/text message:

1. Go to <http://m.privategsm.com> if you want to try **PrivateGSM Professional** or or to <http://e.privategsm.com> if you want to receive **PrivateGSM Enterprise** (PrivateServer PBX required).
2. Read and accept the license and privacy consent terms.
3. Select the model of your device.
4. Select the option **installation via email/SMS message**.
5. Enter your email address or mobile phone number.

Click **Download** to receive an installation email/text message. Click on the link in the message to download the software and launch the installation and activation procedure.



Note

In order to activate Professional version an SMS text message will be sent to a UK PrivateWave number (UK +44). Therefore your SIM card must be enabled to send international text messages and your credit balance must be able to cover these charges.



Based on your subscription plan it is possible that you have to pay data connection fee also when dialing and receiving a secure call. Check the costs of your Internet access on the selected access point before using PrivateGSM. The customer service of your mobile operator may help you in this.

BlackBerry installation

Installer

On BlackBerry platform before installing the actual PrivateGSM application you should download and install an "installer" application that checks if you device is supported or if it could be supported after an OS upgrade (eg: Bold 9000 or Curve 8520 has by default an operative system version of 4.6.x which is not supported, but if you upgrade the OS through Desktop Manager to OS 5.x, PrivateGSM will work on these devices).




figure 1. Click on the link




figure 2. Open the link



figure 3. Download installer




figure 4. Installer report

Installation

PrivateGSM install procedure is very simple: download the application and accept the Application Permission Request. PrivateGSM will start with the License Info screen. You can find the PrivateGSM icon in the BlackBerry applications list.



figure 5. Download PrivateGSM




figure 6. Accept permission request




figure 7. PrivateGSM starts



figure 8. PrivateGSM icon is installed in the application folder

iPhone installation

PrivateGSM for iPhone install procedure is the standard iPhone procedure. Simply click on the SMS and download PrivateGSM through iTunes




figure 9. Click on the link

Android installation

PrivateGSM for Android install procedure follow the standard Android procedure. Simply click on the SMS and download PrivateGSM through Google Play




figure 10. Click on the link




figure 11. Confirm download

PC installation

You can download the installation package of PrivateGSM to your PC and install it on your phone via Bluetooth or with an USB cable.

To download, install and activate software via PC:

1. Open <http://m.privategsm.com> if you want to try **PrivateGSM Professional** or open <http://e.privategsm.com> if you want to receive **PrivateGSM Enterprise** (PrivateServer PBX required).
2. Read and accept the license and privacy consent terms.
3. Select your phone model.

4. Select option **via PC**.

Click **Download**, save the file on your PC and install it on your phone via Bluetooth or USB cable.

BlackBerry Desktop manager

1. Connect your phone to the PC via USB port.
2. Unzip PrivateGSM zip archive, containing .COD and .ALX files
3. Run **Desktop Manager**, connect your phone and add a new application, selecting .ALX file

[PrivateGSM installation pre-requisites](#)

[PrivateGSM Enterprise Activation Wizard](#)