

2.7.1 Provisioning Profile

1. Provisioning profile

Provisioning profile is a PrivateWave configuration template, that can be re-used across different VoIP accounts. It is possible to create different provisioning profile, depending on organization and groups of users.

Provisioning profile can be assigned to a group, as a default profile for all VoIP account in that group. It is possible to assign a provisioning profile to a specific VoIP account, overriding the group configuration.

CSR can select and assign a specific provisioning profile.

Show ProvisioningProfile

General Options	Mutual Authentication Options	Certificate Pinning Options
Name: default	Mutual Authentication: True	SSL Pinning: False
pTime: 100	Server Cert. Name: *.privatewave.eu.cer	Server Cert. Name: *.privatewave.eu.cer
Customer Service Email: support@privatewave.com	Client Cert. Extension: .pem	Server Cert. Download URL: https://download.privatewave.com/download/cert
SIP Proxy Port:	Client Generic Cert. Name: pw_client(dev).p12	User for Server Cert. Download: developer
Logging: True	Cert. Password: pw_client	Psw for Server Cert. Download: pwave2017.
Logging Level: DEBUG	Server Cert. Download URL: https://download.privatewave.com/download/cert	
Dialing timeout: 120	Client Cert. Download URL: https://download.privatewave.com/download/cert	
Ringing timeout: 120	User for Client Cert. Download: developer	
Connecting timeout: 30	Psw for Client Cert. Download: pwave2017.	
Dialing timeout: 90	S/MIME: False	
Disconnecting timeout: 10	CSR: False	
Read only settings: False	CSR Extension: .csr	
Multilevel Security: True	Country Name: Italy	
Enable messaging: True	Organization Name: PrivateWave	
User can edit history log size: True	Organizational Unit Name: PrivateWave	
History log size: 50	Common Name: PrivateWave Client	
PIN: OPTIONAL	Locality Name: Milano	
PIN cache timeout: 600	State or Province Name: Milano	
PIN max retries: 5	Email Address: support@privatewave.com	
PIN lock time: 60	Street Address: via Gaetano Giardino 1	
Enable read notification: True	Postal Code: 20123	
User can enable-disable read notification: True	Title: title	
Message expiration: OPTIONAL	Email for send CSR: test@privatewave.com	
Message expiration timeout: 2	CSR Email Subject: CSR - Certificate Signing Request in Attachment	
	CSR Email Body: CSR - Certificate Signing Request in Attachment	

figure 1. default provisioning profile

By default the appliance comes with a default provisioning profile (shown in [figure 1. default provisioning profile](#)).

2. Create a new provisioning profile

In order to create a new provisioning profile you have to press the "New ProvisioningProfile" button and get a new profile form as below:

Create ProvisioningProfile

General Options	Mutual Authentication Options	Certificate Pinning Options
Name: *	Mutual Authentication: <input type="checkbox"/>	SSL Pinning: <input type="checkbox"/>
pTime: 100	Server Cert. Name:	Server Cert. Name:
Customer Service Email: *	Client Cert. Extension:	Server Cert. Download URL:
SIP Proxy Port:	Client Generic Cert. Name:	User for Server Cert. Download:
Logging: <input checked="" type="checkbox"/>	Cert. Password:	Psw for Server Cert. Download:
Logging Level: INFO ▼	Server Cert. Download URL:	
Dialing timeout: 120	Client Cert. Download URL:	
Ringing timeout: 120	User for Client Cert. Download:	
Connecting timeout: 30	Psw for Client Cert. Download:	
Dialing timeout: 90	S/MIME: <input type="checkbox"/>	
Disconnecting timeout: 10	CSR: <input type="checkbox"/>	
Read only settings: <input checked="" type="checkbox"/>	CSR Extension:	
Multilevel Security: <input type="checkbox"/>	Country Name:	
Enable messaging: <input checked="" type="checkbox"/>	Organization Name:	
User can edit history log size: <input checked="" type="checkbox"/>	Organizational Unit Name:	
History log size: 50 ▼	Common Name:	
PIN: MANDATORY ▼	Locality Name:	
PIN cache timeout: 600	State or Province Name:	
PIN max retries: 5	Email Address:	
PIN lock time: 900	Street Address:	
Enable read notification: <input checked="" type="checkbox"/>	Postal Code:	
User can enable-disable read notification: <input checked="" type="checkbox"/>	Title:	
Message expiration: OPTIONAL ▼	Email for send CSR:	
Message expiration timeout: 15	CSR Email Subject:	
	CSR Email Body:	

figure 2. new provisioning profile

✓ The provisioning profile can contain an OEM license code that can be used during the initial license activation.

✓ The only mandatory fields are the provisioning profile name and the customer service email.

2.1. Options useful for customer support

Most of the field can be left as by default. You probably need to fill:

- **Customer Service Phone:** number to be called to reach the customer service
- **Customer Service Email:** email that will receive the logs and the complaints about the issues
- **Logging:** it's not mandatory but still very suggested to enable the logging in the clients for possible troubleshooting analysis
- **Read only settings:** very handy to keep the application control. This wouldn't let the user to change the settings by his/hers own.

2.2. Secure Messaging options

- **Enable Messaging:** enables Secure Messaging feature on PrivateWave .

! By default this option is set to enabled.

✓ If you want your customers to use this feature then you are obliged to check the above option and then you have to provision the new configuration to all the interested clients.

2.3. Privacy options

- **User can edit history log size:** if checked, then customers can change theirs History log size. History is a new way of grouping events occurred on the client, both Secure Calls and Secure Messages. Thus it's an important privacy subject how many events can stay in the History list.
- **History log size:** In case users were not able to set their history size it could be convenient to decide a maximum amount of events to be shown client side. This option is where you can take this decision. Please consider that default value is 50 events per user.

i As History groups events by the contact's numbers they occurred to, then History size number is to be meant as per contact's number. Eg: if there's a 50 events value set in History log size, each contact listed in History can show up to 50 events. 10 contacts who had events with a customer then create 500 (50 max events list * 10 contacts) history log lines, all grouped by contact's number.

Once you completed to fill the form you can proceed with the profile creation just pressing the "Create" button at the bottom.

Show ProvisioningProfile

i ProvisioningProfile 15 created

Name: My_provisioning_profile

figure 3. new provisioning profile created

2.4. PIN options

- **PIN:** configure if PIN is OPTIONAL or MANDATORY on clients
- **PIN cache timeout:** configure how many seconds PIN is cached, before asking again the PrivateWave 's user to input his own PIN
- **PIN max retries:** how many times user can insert the wrong PIN number, before PrivateWave is locked
- **PIN lock time:** how many seconds PrivateWave remains locked, before user is able again to input the right PIN, after he inserted the wrong one "PIN max retries" times.

2.5. Read Notification

- **Enable read notification:** this option is to configure if client have to send read notification when a secure message is read.
- **User can enable-disable read notification:** this option is to let user to enable or disable read notification feature from client setting screen.

2.6. Message expiration

- **Message expiration:** this options make sense when PIN is enabled. If set to OPTIONAL messages will not expire automatically otherwise if set to MANDATORY messages will expire automatically after "Message expiration timeout"
- **Message expiration timeout:** how many minutes messages remains readable after beeing read the first time when PIN is enabled and "Message expiration" is MANDATORY.



When PIN is not enabled messages automatically expires after 15 minutes

2.7. Mutual authentication

Mutual authentication requires a client authentication through X.509 certificate. This are some options required for client enrollment. In order to make mutual authentication work the following steps are needed

1. server certificate has to be copied in **/data/shared/client_cert** in DER format:

```
openssl x509 -in server_certificate.pem -inform pem -outform der -out server_certificate.der
```

2. certificate of the issuer (CA) of the client certificate has to be inserted in Certification Authority List as described in [2.3 Certificates management](#)
3. TCP port 9443, used by client to download certificate during the provisioning, has to opened in firewall rules:

```
iptables -I INPUT 10 -i <nic> -p tcp -m tcp --dport 9443 -j ACCEPT  
  
service iptables save
```

4. If "CSR encrypted" is enabled than CSR generated by client has to be decrypted through the web page Open configuration -> Client Provisioning -> CSR Decryption

5. Once the certificates has been signed has to be copied in **/data/shared/client_cert** and the file name must <username>.pem
6. In order to use a generic certificate (the same for each client) it has to be copied in **/data/shared/client_cert**

2.8. SSL certificate pinning


SSL certificate pinning is a stronger way for server authentication by the client. Clients are strictly

2.9. Edit a provisioning profile

From the Provisioning Profile list, choose the profile you need to edit and click on it with your mouse. the "Show Provisioning Profile" page will appear (see [figure 3. new provisioning profile created](#)).

Press the **"Edit"** button.

Show ProvisioningProfile

 ProvisioningProfile 15 updated

Name:

My_provisioning_profile

figure 4. Provisioning Profile edit form

Change the fields you need to and when you're done press the **"Update"** button at the bottom of the form to save the changes.

3. Delete a Provisioning Profile

By the very same form shown above in [figure 3. new provisioning profile created](#) you can also delete your Provisioning Profile.

You have to click on the "Delete" button and Confirm the operation by clicking "Ok" in the warning pop-up window. The Profile should be gone.